


# Mdx Platform Architecture Overview



## Movement methods:

### Method identifier:

"raw" - array of raw values indicating length of the six muscles

"xyzrpy" - array of six values for xyz translations and rotations

x translation is forward/backward movement (surge)

y translation is side to side movement (sway)

z translation is up/down movement (heave)

x rotation is tilting on front/back axis (roll)

y rotation is tilting on lateral axis (pitch)

z rotation is tilting on vertical axis (yaw)

argument units default to normalized values (range between  $\pm 1.0$ )

In future, "units": "real" can be included in message to provide real world mm values for translation, degrees for rotation

### args:

An array of six floating point values

Example: send command with 10% heave (upward movement), -20% roll (bank)

```
{"jsonrpc": "2.0", "method": "xyzrpy", "args": [0.0, 0.0, 0.1, -0.2, 0.0, 0.0]}
```

## Configuration Method: - identifier "config"

(each of the following arguments is optional)

"blocking" true/false - (current version only supports false)

"gainX" float multiplier for x values

"gainY" float multiplier for y values

"gainZ" float multiplier for z values

"gainRoll" float multiplier for roll values

"gainPitch" float multiplier for pitch values

"gainYaw" float multiplier for yaw values

"gain" float multiplier for all 6 DOF

- all above gain factors default to 1.0

"washoutX" washout factor for x values

"washoutY" washout factor for y values

"washoutZ" washout factor for z values

"washoutRoll" washout factor for roll values

"washoutPitch" washout factor for pitch values

"washoutYaw" washout factor for yaw values

- washouts default to 1.0, lower numbers increase the rate values will decay to 0

Example: set overall gain to 0.5 and yaw washout to 0.996

```
{"jsonrpc": "2.0", "method": "config", "gain": 0.5, "washoutYaw": 0.996}
```